

Fast Track PC Software (PCSS) Installation Programming Guide


****3000 Series Timers: ALWAYS install PCSS Software**

****2000 Series Timers: Only install PCSS Software if PC Software Site License was purchased by customer. Contact Delphi Fast Track Customer Support to turn on PCSS Port if installing for an existing 2000 Series Timer**

1. Insert Delphi supplied USB Flash Drive into an available USB port on the PC that will be running the PCSS Software
2. Locate and double click the **"Fast Track PC Software Setup.exe"** file to install the Fast Track PC Software and follow installation steps
3. Click on the FastTrack.exe file located at **START → Programs → Fast Track PC Software Suite → FastTrack.exe**
4. **Choose only one:**
 - a. If the customer will be using a network **ONLY** connection, just click **"OK"** in the Direct Port Configuration Window
 - b. If the customer will be using a serial connection or serial **AND** network, in the Direct Port Configuration window, specify the proper **Port** to be used along with the proper **Baud** rate (9600 for Carl's Jr / Hardees; 115200 for all others), then click **"OK"**.
5. If the Installer knows the IP address for the timer, skip to step 13. If the IP address of the timer is not known, click the **"Cancel"** button in the **"Site Configuration"** window to close it, then proceed to step 6.
6. On the top menu bar, Select **"Config"**
7. Select **"Network E3"**
8. The network utility will locate the Fast Track Timer on the network and display settings
9. Verify that the IP Address, Gateway and Subnet Mask are correct for the timer on the local network. Also verify the PCSS PORT = 4660.
 - a. If the settings are correct, click **"Exit"**
 - b. If the settings are NOT correct, click **"Configure"**, then enter the proper settings and click **"OK"**, then click **"Exit"**
10. On the top menu bar, Select **"Site"**
11. Click **"Add Site"**
12. In the **"Site"** box, enter a name for the site of the customer's choosing (Site Name is typically be the store number)
13. For **Connect Type**, select **TCP/IP** for an Ethernet Connection; **or** if serial connection, select **"Direct"**
14. Enter the **IP ADDRESS** for the site for Ethernet; **or** if serial connection, select **"Default"** for Baud Rate.
15. Click **"Apply"**
16. Click **"OK"**
17. On the top menu bar, select **"Download"**
18. Make sure the Site just created is highlighted, then check the box **"Disconnect When Finished"**
19. Click **"Single -Site"**
20. The PC should connect to the timer and perform a complete download.
21. If **YES**, Click **"Exit"** and close the Fast Track PC Software.
22. If **NO**, verify connections, IP address and settings, and repeat steps 17-21.

Delphi Fast Track Customer Support: 1-800-456-0060

Equipment Layout



Important Notes

- Both the Fast Track Timer and the PC should be plugged into the same local area network (LAN)
- The Fast Track PC Software (PCSS) port numbers should communicate freely over the local area network (LAN)
- Remote access is gained by port forwarding through the router.
- **Default Port Settings:**
 - **Port #4660 – Fast Track PC Software**
 - **Settings can be adjusted to meet customer's networking requirements.**

Local PC System Requirements

- Windows 2000, XP w/Service pack 2, Vista, Windows 7
- Windows .NET Framework 2.0 (or higher)
- 133Mhz Pentium or greater
- At least 10Mb of free hard disk space
- (additional space is required for Log File)
- 32 Mb of RAM
- USB 2.0
- One or more Network Interface Card
- **Administrative Rights**